

Installation Guide

Z510 / Windows98 / USB Direct Cable (by Prolific)

Handset:	Error! Bookmark not defined.
USB cable installation	1
Modem installation	3
Dial Up Configuration	7



Setting the modem speed to 230K

Press Menu
Press 8
Press 2
Press 2
Select "Packet 230K" option
OK
Press Back
End

USB cable installation

Connect the handset to PC using the USB Direct Cable (by Prolific). The Operating System will launch "Found New Hardware Wizard".



Click Next




Search for the best driver for your device.



Specify a location.

Note: USB Direct Cable (by Prolific) is delivered with it's own drivers (Floppy or CD).

If the installation is successful you shall see a new COM port in Device Manager
My Computer > Control Panel > System > Device Manager > Ports (COM & LPT)





USB to Serial Port (COM*)


Modem installation

Note: the H-100 is equipped with a built-in modem, which means you don't need to buy a modem if you want to connect to Internet using a dial-up connection. For this reason, the PC/laptop needs to be set-up in a similar scenario as an external modem set-up. This paragraph will guide you through the steps you need to follow in order to get this modem installed.


After you closed all your running applications (recommended), click the Windows Start button and go to Control Panel.



Double click "Modems" icon within the Control Panel
Press Add New Modem



Click the check box named "Don't detect my modem; I will select it from a list"; click next;



Click: Have Disk


Click next

Select the proper communication port (example: COM2) to which your CDMA device is connected.

Dial Up Configuration

Open My Computer

Open Dial Up Networking




Make New Connection

Type a name for the connection (like "ZappMobile")


Select Modem – Zapp CDMA Handset (With USB 230k serial conv)

Click Next



Enter the Telephone number: #777


Select country or region code: Romania (40)



Click next




Click Finish.




Double click the connection you have just made (example: Zapp Mobile)




Enter any username. The Password field has no importance for the time being. Click connect. It takes a few seconds until the computer shall be connected.



When connected you may see this message



(you may choose not to see this message in the future)



When connection is established you shall see the following icon in the lower right corner of the screen.

